## **I2C** Ten-bit Addresses

The I2C protocol knows about two kinds of device addresses: normal 7 bit addresses, and an extended set of 10 bit addresses. The sets of addresses do not intersect: the 7 bit address 0x10 is not the same as the 10 bit address 0x10 (though a single device could respond to both of them). To avoid ambiguity, the user sees 10 bit addresses mapped to a different address space, namely 0xa000-0xa3ff. The leading 0xa (= 10) represents the 10 bit mode. This is used for creating device names in sysfs. It is also needed when instantiating 10 bit devices via the new device file in sysfs.

I2C messages to and from 10-bit address devices have a different format. See the I2C specification for the details.

The current 10 bit address support is minimal. It should work, however you can expect some problems along the way:

- Not all bus drivers support 10-bit addresses. Some don't because the hardware doesn't support them (SMBus doesn't require 10-bit address support for example), some don't because nobody bothered adding the code (or it's there but not working properly.) Software implementation (i2c-algo-bit) is known to work.
- Some optional features do not support 10-bit addresses. This is the case of automatic detection and instantiation of devices by their, drivers, for example.
- Many user-space packages (for example i2c-tools) lack support for 10-bit addresses.

Note that 10-bit address devices are still pretty rare, so the limitations listed above could stay for a long time, maybe even forever if nobody needs them to be fixed.