

Instrumenting CPython with DTrace and SystemTap

Author: David Malcolm

Author: Łukasz Langa

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 1)
```

Unknown directive type "highlight".

```
.. highlight:: shell-session
```

DTrace and SystemTap are monitoring tools, each providing a way to inspect what the processes on a computer system are doing. They both use domain-specific languages allowing a user to write scripts which:

- filter which processes are to be observed
- gather data from the processes of interest
- generate reports on the data

As of Python 3.6, CPython can be built with embedded "markers", also known as "probes", that can be observed by a DTrace or SystemTap script, making it easier to monitor what the CPython processes on a system are doing.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 25)
```

Unknown directive type "impl-detail".

```
.. impl-detail::
```

```
DTrace markers are implementation details of the CPython interpreter.
No guarantees are made about probe compatibility between versions of
CPython. DTrace scripts can stop working or work incorrectly without
warning when changing CPython versions.
```

Enabling the static markers

macOS comes with built-in support for DTrace. On Linux, in order to build CPython with the embedded markers for SystemTap, the SystemTap development tools must be installed.

On a Linux machine, this can be done via:

```
$ yum install systemtap-sdt-devel
```

or:

```
$ sudo apt-get install systemtap-sdt-dev
```

CPython must then be `option`configured with the --with-dtrace option <--with-dtrace>`:`

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 49); backlink
```

Unknown interpreted text role "option".

```
System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 52)
```

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none
```

```
checking for --with-dtrace... yes
```

On macOS, you can list available DTrace probes by running a Python process in the background and listing all probes made available by the Python provider:

```
$ python3.6 -q &
```

```
$ sudo dtrace -l -P python$! # or: dtrace -l -m python3.6
```

ID	PROVIDER	MODULE	FUNCTION NAME
29564	python18035	python3.6	_PyEval_EvalFrameDefault function-entry
29565	python18035	python3.6	dtrace_function_entry function-entry
29566	python18035	python3.6	_PyEval_EvalFrameDefault function-return
29567	python18035	python3.6	dtrace_function_return function-return
29568	python18035	python3.6	collect gc-done
29569	python18035	python3.6	collect gc-start
29570	python18035	python3.6	_PyEval_EvalFrameDefault line
29571	python18035	python3.6	maybe_dtrace_line line

On Linux, you can verify if the SystemTap static markers are present in the built binary by seeing if it contains a ".note.stapsdt" section.

```
$ readelf -S ./python | grep .note.stapsdt
[30] .note.stapsdt          NOTE              0000000000000000 00308d78
```

If you've built Python as a shared library (with the `option: '--enable-shared'` configure option), you need to look instead within the shared library. For example:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 81); [backlink](#)
Unknown interpreted text role "option".

```
$ readelf -S libpython3.3dm.so.1.0 | grep .note.stapsdt
[29] .note.stapsdt          NOTE              0000000000000000 00365b68
```

Sufficiently modern readelf can print the metadata:

```
$ readelf -n ./python

Displaying notes found at file offset 0x00000254 with length 0x00000020:
  Owner          Data size      Description
  GNU            0x00000010      NT_GNU_ABI_TAG (ABI version tag)
    OS: Linux, ABI: 2.6.32

Displaying notes found at file offset 0x00000274 with length 0x00000024:
  Owner          Data size      Description
  GNU            0x00000014      NT_GNU_BUILD_ID (unique build ID bitstring)
    Build ID: df924a2b08a7e89f6e11251d4602022977af2670

Displaying notes found at file offset 0x002d6c30 with length 0x00000144:
  Owner          Data size      Description
  stapsdt        0x00000031      NT_STAPSDT (SystemTap probe descriptors)
    Provider: python
    Name: gc_start
    Location: 0x0000000004371c3, Base: 0x0000000000630ce2, Semaphore: 0x00000000008d6bf6
    Arguments: -4@%ebx
  stapsdt        0x00000030      NT_STAPSDT (SystemTap probe descriptors)
    Provider: python
    Name: gc_done
    Location: 0x0000000004374e1, Base: 0x0000000000630ce2, Semaphore: 0x00000000008d6bf8
    Arguments: -8@%rax
  stapsdt        0x00000045      NT_STAPSDT (SystemTap probe descriptors)
    Provider: python
    Name: function_entry
    Location: 0x000000000053db6c, Base: 0x0000000000630ce2, Semaphore: 0x00000000008d6be8
    Arguments: 8@%rbp 8@%r12 -4@%eax
  stapsdt        0x00000046      NT_STAPSDT (SystemTap probe descriptors)
    Provider: python
    Name: function_return
    Location: 0x000000000053dba8, Base: 0x0000000000630ce2, Semaphore: 0x00000000008d6bea
    Arguments: 8@%rbp 8@%r12 -4@%eax
```

The above metadata contains information for SystemTap describing how it can patch strategically-placed machine code instructions to enable the tracing hooks used by a SystemTap script.

Static DTrace probes

The following example DTrace script can be used to show the call/return hierarchy of a Python script, only tracing within the invocation of a function called "start". In other words, import-time function invocations are not going to be listed:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 138)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

    self int indent;

python$target::function-entry
/copyinstr(arg1) == "start"/
{
    self->trace = 1;
}

python$target::function-entry
/self->trace/
{
    printf("%d\t%s:", timestamp, 15, probename);
    printf("%s", self->indent, "");
    printf("%s:%s:%d\n", basename(copyinstr(arg0)), copyinstr(arg1), arg2);
    self->indent++;
}

python$target::function-return
/self->trace/
{
    self->indent--;
    printf("%d\t%s:", timestamp, 15, probename);
    printf("%s", self->indent, "");
    printf("%s:%s:%d\n", basename(copyinstr(arg0)), copyinstr(arg1), arg2);
}

python$target::function-return
/copyinstr(arg1) == "start"/
{
    self->trace = 0;
}
```

It can be invoked like this:

```
$ sudo dtrace -q -s call_stack.d -c "python3.6 script.py"
```

The output looks like this:

System Message: WARNING/2 (D: \onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 178)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

156641360502280 function-entry:call_stack.py:start:23
156641360518804 function-entry: call_stack.py:function_1:1
156641360532797 function-entry: call_stack.py:function_3:9
156641360546807 function-return: call_stack.py:function_3:10
156641360563367 function-return: call_stack.py:function_1:2
156641360578365 function-entry: call_stack.py:function_2:5
156641360591757 function-entry: call_stack.py:function_1:1
156641360605556 function-entry: call_stack.py:function_3:9
156641360617482 function-return: call_stack.py:function_3:10
156641360629814 function-return: call_stack.py:function_1:2
156641360642285 function-return: call_stack.py:function_2:6
156641360656770 function-entry: call_stack.py:function_3:9
156641360669707 function-return: call_stack.py:function_3:10
156641360687853 function-entry: call_stack.py:function_4:13
156641360700719 function-return: call_stack.py:function_4:14
156641360719640 function-entry: call_stack.py:function_5:18
156641360732567 function-return: call_stack.py:function_5:21
156641360747370 function-return:call_stack.py:start:28
```

Static SystemTap markers

The low-level way to use the SystemTap integration is to use the static markers directly. This requires you to explicitly state the binary file containing them.

For example, this SystemTap script can be used to show the call/return hierarchy of a Python script:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 210)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

    probe process("python").mark("function__entry") {
        filename = user_string($arg1);
        funcname = user_string($arg2);
        lineno = $arg3;

        printf("%s => %s in %s:%d\\n",
            thread_indent(1), funcname, filename, lineno);
    }

    probe process("python").mark("function__return") {
        filename = user_string($arg1);
        funcname = user_string($arg2);
        lineno = $arg3;

        printf("%s <= %s in %s:%d\\n",
            thread_indent(-1), funcname, filename, lineno);
    }
```

It can be invoked like this:

```
$ stap \
  show-call-hierarchy.stp \
  -c "./python test.py"
```

The output looks like this:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 238)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

11408 python(8274):      => __contains__ in Lib/_abcoll.py:362
11414 python(8274):      => __getitem__ in Lib/os.py:425
11418 python(8274):      => encode in Lib/os.py:490
11424 python(8274):      <= encode in Lib/os.py:493
11428 python(8274):      <= __getitem__ in Lib/os.py:426
11433 python(8274):      <= __contains__ in Lib/_abcoll.py:366
```

where the columns are:

- time in microseconds since start of script
- name of executable
- PID of process

and the remainder indicates the call/return hierarchy as the script executes.

For a `option: '--enable-shared'` build of CPython, the markers are contained within the libpython shared library, and the probe's dotted path needs to reflect this. For example, this line from the above example:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 257); [backlink](#)

Unknown interpreted text role "option".

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 261)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

    probe process("python").mark("function__entry") {
```

should instead read:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 267)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

    probe process("python").library("libpython3.6dm.so.1.0").mark("function__entry") {
```

(assuming a `ref` debug build <debug-build>`` of CPython 3.6)

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 271); [backlink](#)

Unknown interpreted text role "ref".

Available static markers

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 277)

Unknown directive type "object".

```
.. object:: function__entry(str filename, str funcname, int lineno)

    This marker indicates that execution of a Python function has begun.
    It is only triggered for pure-Python (bytecode) functions.

    The filename, function name, and line number are provided back to the
    tracing script as positional arguments, which must be accessed using
    ``$arg1``, ``$arg2``, ``$arg3``:

    * ``$arg1`` : ``(const char *)`` filename, accessible using ``user_string($arg1)``
    * ``$arg2`` : ``(const char *)`` function name, accessible using
      ``user_string($arg2)``
    * ``$arg3`` : ``int`` line number
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 293)

Unknown directive type "object".

```
.. object:: function__return(str filename, str funcname, int lineno)

    This marker is the converse of :c:func:`function__entry`, and indicates that
    execution of a Python function has ended (either via ``return``, or via an
    exception). It is only triggered for pure-Python (bytecode) functions.

    The arguments are the same as for :c:func:`function__entry`
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 301)

Unknown directive type "object".

```
.. object:: line(str filename, str funcname, int lineno)

    This marker indicates a Python line is about to be executed. It is
    the equivalent of line-by-line tracing with a Python profiler. It is
    not triggered within C functions.

    The arguments are the same as for :c:func:`function__entry`.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 309)

Unknown directive type "object".

```
.. object:: gc__start(int generation)
```

Fires when the Python interpreter starts a garbage collection cycle. ``arg0`` is the generation to scan, like :func:`gc.collect()`.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 314)

Unknown directive type "object".

```
.. object:: gc__done(long collected)
```

Fires when the Python interpreter finishes a garbage collection cycle. ``arg0`` is the number of collected objects.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 319)

Unknown directive type "object".

```
.. object:: import__find__load__start(str modulename)
```

Fires before :mod:`importlib` attempts to find and load the module. ``arg0`` is the module name.

```
.. versionadded:: 3.7
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 326)

Unknown directive type "object".

```
.. object:: import__find__load__done(str modulename, int found)
```

Fires after :mod:`importlib`'s find_and_load function is called. ``arg0`` is the module name, ``arg1`` indicates if module was successfully loaded.

```
.. versionadded:: 3.7
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 335)

Unknown directive type "object".

```
.. object:: audit(str event, void *tuple)
```

Fires when :func:`sys.audit` or :c:func:`PySys_Audit` is called. ``arg0`` is the event name as C string, ``arg1`` is a :c:type:`PyObject` pointer to a tuple object.

```
.. versionadded:: 3.8
```

SystemTap Tapsets

The higher-level way to use the SystemTap integration is to use a "tapset": SystemTap's equivalent of a library, which hides some of the lower-level details of the static markers.

Here is a tapset file, based on a non-shared build of CPython:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 353)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none
```

```

/*
   Provide a higher-level wrapping around the function__entry and
   function__return markers:
*/
probe python.function.entry = process("python").mark("function__entry")
{
    filename = user_string($arg1);
    funcname = user_string($arg2);
    lineno = $arg3;
    frameptr = $arg4
}
probe python.function.return = process("python").mark("function__return")
{
    filename = user_string($arg1);
    funcname = user_string($arg2);
    lineno = $arg3;
    frameptr = $arg4
}

```

If this file is installed in SystemTap's tapset directory (e.g. /usr/share/systemtap/tapset), then these additional probepoints become available:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 378)

Unknown directive type "object".

```
.. object:: python.function.entry(str filename, str funcname, int lineno, frameptr)
```

This probe point indicates that execution of a Python function has begun.
It is only triggered for pure-Python (bytecode) functions.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 383)

Unknown directive type "object".

```
.. object:: python.function.return(str filename, str funcname, int lineno, frameptr)
```

This probe point is the converse of ``python.function.return``, and indicates that execution of a Python function has ended (either via ``return``, or via an exception). It is only triggered for pure-Python (bytecode) functions.

Examples

This SystemTap script uses the tapset above to more cleanly implement the example given above of tracing the Python function-call hierarchy, without needing to directly name the static markers:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\ (cpython-main) (Doc) (howto) instrumentation.rst, line 397)

Cannot analyze code. No Pygments lexer found for "none".

```

.. code-block:: none

probe python.function.entry
{
    printf("%s => %s in %s:%d\n",
           thread_indent(1), funcname, filename, lineno);
}

probe python.function.return
{
    printf("%s <= %s in %s:%d\n",
           thread_indent(-1), funcname, filename, lineno);
}

```

The following script uses the tapset above to provide a top-like view of all running CPython code, showing the top 20 most

frequently-entered bytecode frames, each second, across the whole system:

System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\cpython-main) (Doc) (howto) instrumentation.rst, line 416)

Cannot analyze code. No Pygments lexer found for "none".

```
.. code-block:: none

global fn_calls;

probe python.function.entry
{
    fn_calls[pid(), filename, funcname, lineno] += 1;
}

probe timer.ms(1000) {
    printf("\033[2J\033[1;1H") /* clear screen */
    printf("%6s %80s %6s %30s %6s\n",
        "PID", "FILENAME", "LINE", "FUNCTION", "CALLS")
    foreach ([pid, filename, funcname, lineno] in fn_calls- limit 20) {
        printf("%6d %80s %6d %30s %6d\n",
            pid, filename, lineno, funcname,
            fn_calls[pid, filename, funcname, lineno]);
    }
    delete fn_calls;
}
```